

# Menu Route Map

## Preferences

### Display Settings

- Default Screen After Startup/Restoration
  - Home
  - Copy
  - Fax\*
  - Scan
  - Secure Print
  - Status Monitor
    - Home, Copy, Fax\*, Scan, Secure Print
- Home Screen Button Display Settings
  - Select Button to Display
    - Favorite Copy Settings
    - Favorite Fax Settings\*
    - Favorite Scan Settings
    - Set Display Order
- Language
  - Deutsch, English, Español, Français, Italiano, Português, 日本語, 中文(繁體), 中文(简体), 한국어
- Remote UI Language
  - English, Japanese, French, Spanish, German, Italian, Portuguese, Chinese (Simplified), Chinese (Traditional), Korean
- Notify to Clean Orig. Scan Area
  - Off, On
- Millimeter/Inch Entry Switch
  - Millimeter, Inch
- Gram/Pound Switch
  - Gram, Pound
- Display Timing for Cart. Prep.
  - Auto
    - Off
    - Custom
      - On
- Display Notif. to Clean Fixing Assembly
  - Off, On
- Show Warnings
  - Off, On
- Action When Warning
  - Low Cartridge Level
    - Continue Printing, Stop Printing
- Display IP Address
  - Off, On

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.

### English Keyboard Layout

- USA Layout
- UK Layout

### Timer/Energy Settings

- Current Date/Time Settings
- Date/Time Settings
  - Time Zone
    - (UTC-12:00) International Date Line West to (UTC-05:00) Eastern Time (US & Canada) to (UTC+14:00) Kiribati Island
  - Daylight Saving Time Settings
    - Off
    - On
      - Start: Month, Week, Day
      - End: Month, Week, Day
  - Date Format
    - YYYY MM/DD, MM/DD/YYYY, DD/MM YYYY
  - Time Format
    - 12 Hour (AM/PM), 24 Hour
  - Auto Reset Time
    - Set This Function
      - Off
      - On
        - Set Time
          - 1 to 2 to 9 (min.)
  - Function After Auto Reset
    - Default Function, Selected Function
  - Auto Sleep Time
    - 1 to 120 (min.)
  - Auto Sleep Daily Timer
    - Set This Function
      - Off
      - On
        - (0:00 to 12:59 AM/PM)
  - Sleep Mode Exit Time Settings
    - Set This Function
      - Off
      - On
        - (0:00 to 12:59 AM/PM)

### Network

- Select Wired/Wireless LAN
  - Wired LAN, Wireless LAN
- Wireless LAN Settings
  - Other Connections
    - Manually Enter Network Name (SSID)
    - Security Settings
      - None
      - WEP
        - Encryption Key 1 to 4
      - WPA/WPA2-PSK
        - Encryption Key 1 to 4
        - Auto, AES-CCMP
    - WPS Push Button Mode
    - WPS PIN Code Mode
    - Connection Set.
      - Power Save Mode
        - Off, On
      - Connection Information
        - MAC Address
        - Wireless LAN Status
        - Latest Error Information
        - Channel
        - Network Name
        - Security Settings
        - Power Save Mode
  - Direct Connection Settings
    - Use Direct Connection
      - Off
      - On
        - Direct Connection Termination
          - Automatically Terminate Session
            - Off
            - On
              - Time Until Session Terminates
                - 1 to 60 (min.)
        - Access Point Mode Settings
          - Use Custom SSID
            - Off
            - On
              - SSID
          - Use Custom Network Key
            - Off
            - On
              - Network Key
          - Keep Enabled If SSID/Ntwk Key Spcd
            - Off, On
          - Config. IP Address For Direct Conn.
            - 192.168.22.1
    - Easy Connection via PC

### TCP/IP Settings

- IPv4 Settings
  - IP Address Settings
    - Auto Acquire
      - Auto Acquire
        - Off
        - On
          - Select Protocol
            - Off, DHCP
            - Auto IP
              - Off, On
      - Manually Acquire
        - IP Address: 0.0.0.0
        - Subnet Mask: 0.0.0.0
        - Gateway Address: 0.0.0.0
      - Check Settings
    - DHCP Option Settings
      - Acquire Host Name
        - Off, On
      - DNS Dynamic Update
        - Off, On
      - Acquire DNS Server Address
        - Off, On
      - Acquire Domain Name
        - Off, On
      - Acquire WINS Server Address
        - Off, On
      - Acquire SMTP Server Address
        - Off, On
      - Acquire POP Server Address
        - Off, On
    - PING Command
  - IPv6 Settings
    - Use IPv6
      - Off
      - On
        - Stateless Address Settings
          - Stateless Address Settings
            - Off, On
          - Check Settings
            - Stateless Address
              - Prefix Length
          - DHCPv6 Settings
            - Use DHCPv6
              - Off, On
            - Check Settings
              - Stateful Address
                - Prefix Length
            - DHCP Option Settings
              - Acquire DNS Server Address
                - Off, On
              - Acquire Domain Name
                - Off, On
    - DNS Settings
      - IPv4 DNS Server Address Settings
        - Primary DNS Server: 0.0.0.0
        - Secondary DNS Server: 0.0.0.0
      - DNS Host Name/Domain Name Settings
        - IPv4
          - Host Name
          - Domain Name
        - IPv6
          - Use IPv4 Host/Domain
            - Off
            - On
              - Host Name
              - Domain Name
        - DNS Dynamic Update Settings
          - IPv4
            - DNS Dynamic Update
              - Off
              - On
                - DNS Dynamic Update Interval
                  - 0 to 24 to 48 (hr.)
            - IPv6
              - DNS Dynamic Update
                - Off
                - On
                  - Register Manual Address
                    - Off, On
                  - Register Stateful Address
                    - Off, On
                  - Register Stateless Address
                    - Off, On
                  - DNS Dynamic Update Interval
                    - 0 to 24 to 48 (hr.)
            - mDNS Settings
              - IPv4
                - Use mDNS
                  - Off
                  - On
                    - mDNS Name
                - IPv6
                  - Use mDNS
                    - Off
                    - On
                      - Use Same mDNS Name as IPv4
                        - Off
                        - On
                          - mDNS Name
              - WINS Settings
                - WINS Resolution
                  - Off
                  - On
                - WINS Server Address: 0.0.0.0
              - LPD Settings
                - Use LPD Printing
                  - Off, On
                - RX Timeout
                  - 1 to 5 to 60 (min.)
              - RAW Settings
                - Use RAW Printing
                  - Off, On
                - RX Timeout
                  - 1 to 5 to 60 (min.)
              - WSD Settings
                - Use WSD Printing
                  - Off, On
                - Use WSD Browsing
                  - Off, On
                - Use WSD Scanning
                  - Off, On
                - Use Computer Scanning
                  - Off, On
                - Use Multicast Discovery
                  - Off, On
              - Use FTP PASV Mode
                - Off, On
              - Use HTTP
                - Off, On
              - Use IPSec
                - Off, On
              - Port Number Settings
                - LPD
                  - 1 to 515 to 65535
                - RAW
                  - 1 to 9100 to 65535
                - WSD Multicast Discovery
                  - 1 to 3702 to 65535
                - HTTP
                  - 1 to 80 to 65535
                - Multicast Discovery
                  - 1 to 427 to 65535
                - POP3
                  - 1 to 110 to 65535
                - SMTP TX
                  - 1 to 25 to 65535

- FTP
  - 1 to 21 to 65535
- SNMP
  - 1 to 161 to 65535
- MTU Size
  - 1300, 1400, 1500

### SNMP Settings

- SNMPv1 Settings
  - Off, On
- SNMPv3 Settings
  - Off, On
- Acquire Printer Mngt. Info. from Host
  - Off, On
- Format Host Rsrcs. MIB to RFC2790
  - Off, On
- Use Dedicated Port
  - Off, On
- Dedicated Port Auth. Method
  - Mode 1, Mode 2
- Wait Time for Conn. at Startup
  - 0 to 300 (sec.)
- Ethernet Driver Settings
  - Auto Detect
    - Off
      - Communication Mode
        - Half Duplex, Full Duplex
      - Ethernet Type
        - 10BASE-T, 100BASE-TX, 1000BASE-T
    - On
  - MAC Address
- Use IEEE 802.1X
  - Off, On

### Firewall Settings

- IPv4 Address Filter
  - Outbound Filter
    - Off, On
  - Inbound Filter
    - Off, On
- IPv6 Address Filter
  - Outbound Filter
    - Off, On
  - Inbound Filter
    - Off, On
- MAC Address Filter
  - Outbound Filter
    - Off, On
  - Inbound Filter
    - Off, On

### Device Settings Management

- Off, On

### Monitoring Service\*

- Off, On

### RMT-SW

- Off, On

### Initialize Network Settings

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.

### External Interface

- USB Settings
  - Use as USB Device
    - Off, On
  - Use USB Storage Device
    - Off, On

### Accessibility

- Invert Screen Colors
  - Off, On
- Brightness
  - Five Levels
- Message Display Time
  - 1 to 2 to 5 (sec.)

### Adjustment/Maintenance

### Adjust Image Quality

- Adjust Copy Image
- Printer Density
  - Nine Levels
- Toner Save
  - Off, On
- Black Text Processing for Color
  - Feeder
    - Seven Levels
  - Platen Glass
    - Seven Levels
- Adjust Print Position
  - Multi-Purpose Tray
    - Adjust Vertically (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Vertically (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
  - Drawer 1
    - Adjust Vertically (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Vertically (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
  - Drawer 2
    - Adjust Vertically (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Vertically (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))

### Special Processing

- Special Paper Processing
  - Manual Back Side Print (2-Sided Only)
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
    - Drawer 2
      - Off, On
  - Rough Surface Envelope Mode
    - Off, On
  - Paper Wrinkle Correction
    - Off, On
  - Paper Curl Correction
    - Off, On
  - Rdc. Tnr Flaking from Heavy Sml. Ppr
    - Off, On
  - Reduce Thin Paper Curling
    - Off, On
  - Reduce Ppr. Sticking at Output
    - Off, On
  - High Humidity Mode
    - Off, On
  - Low Humidity Mode
    - Off, Mode 1, Mode 2

- Reduce Ghosting 1
  - Off, On
- Rdc Condens. (Consec 2-Sd Prt)
  - Off, On
- Rdc. Wrinkles(Humidity)/Streaks
  - Off, On
- Quiet Mode
  - Off, On
- Correct Blurry Image
  - Off, Mode 1, Mode 2, Mode 3, Mode 4
- Correct Blurry Image for Copy
  - Off, Mode 1, Mode 2, Mode 3
- Rdc Blink Space Dark. After Rplc Cart.
  - Off, On

### Remove Streaks from Scan Area

- Off, On

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.

### Maintenance

#### Clean Fixing Assembly

#### Clean Feeder

#### Control Condensation

- Off
- On

Use Fax Memory Lock, Use Fax Memory Lock + Do Not Allow Job Printing During Process

### Function Settings

### Common

#### Paper Feed Settings

- Paper Source Auto Selection
  - Copy
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
    - Drawer 2
      - Off, On
  - Printer
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
    - Drawer 2
      - Off, On
  - Receiver/Fax
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
    - Drawer 2
      - Off, On
  - Other
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
    - Drawer 2
      - Off, On
- Switch Paper Feed Method
  - Multi-Purpose Tray
    - Speed Priority, Print Side Priority
  - Drawer 1
    - Speed Priority, Print Side Priority
  - Drawer 2
    - Speed Priority, Print Side Priority

#### Print Settings

- Auto Delete Suspended Jobs
  - Set This Function
    - Off
    - On
      - Set Time
        - 0 to 5 to 240 (min.)

#### Scan Settings

- Auto Online
  - Off, On
- Auto Offline
  - Set This Function
    - Off
    - On
      - Set Time
        - 1 to 5 to 60 (min.)

#### Generate File

- Output File Image Settings
  - YCbCr TX Gamma Value
    - Gamma 1.0, Gamma 1.4, Gamma 1.8, Gamma 2.2
- OCR (Text Searchable) Settings
  - Smart Scan
    - Off, On

#### Fax Setup Guide\*

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.



### Copy

#### Change Default Settings (Copy)



- Number of Copies
  - 1 to 999
- Paper Source
  - Multi-Purpose Tray, Drawer 1, Drawer 2, Auto Select
- Density
  - Nine Levels
  - Adjust Background Density
    - Auto
    - Adjust (Manual)
  - Nine Levels
- Copy Ratio
  - Custom Ratio, 100% Direct, Auto, 400% Max, 200%, 129% STMT->LTR, 78% LGL->LTR, 64% LTR->STMT, 50%, 25% Min
- 2-Sided Printing
  - Off, 1-Sided->2-Sided, 2-Sided->2-Sided, 2-Sided->1-Sided, Orig./Fin. Type
- N on 1
  - Off, 2 on 1, 4 on 1, Layout
- Original Type
  - Text, Text/Photo, Text/Photo (High Quality), Photo
- Collate
  - Off, On
- Erase Frame
  - Off, On
- Sharpness
  - Seven Levels

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.



## Menu Route Map




Settings marked with "\*\*\*" may not be displayed depending on the model you are using, options, or other setting items.



Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.




Settings marked with "" may not be displayed depending on the model you are using, options, or other setting items.



Settings marked with "" may not be displayed depending on the model you are using, options, or other setting items.






# Menu Route Map



Set Destination

Address Book PIN

Management Settings



Initialize All Data/Settings