

# Menu Route Map

### Preferences

#### Display Settings

- Default Screen After Startup/Restoration
  - Home
  - Copy
  - Fax
  - Scan
  - Secure Print
  - Status Monitor
    - Home, Copy, Fax, Scan, Secure Print
- Home Screen Button Display Settings
  - Select Button to Display
  - Favorite Copy Settings
  - Favorite Fax Settings
  - Favorite Scan Settings
  - Set Display Order
- Language
  - Deutsch, English, Español, Français, Italiano, Português, 日本語, 中文(繁體), 中文(简体), 한국어
- Remote UI Language
  - English, Japanese, French, Spanish, German, Italian, Portuguese, Chinese (Simplified), Chinese (Traditional), Korean
- Notify to Clean Orig. Scan Area
  - Off, On
- Millimeter/Inch Entry Switch
  - Millimeter, Inch
- Gram/Pound Switch
  - Gram, Pound
- Display Timing for Cart. Prep.
  - Auto
    - Off
    - Custom
    - On
- Show Warnings
  - Off, On
- Action When Warning
  - Low Cartridge Level
    - Continue Printing, Stop Printing
- Display IP Address
  - Off, On

Settings marked with "\*" may not be displayed depending on the model you are using or other setting items.

### English Keyboard Layout

- USA Layout
- UK Layout

### Timer/Energy Settings

#### Current Date/Time Settings

#### Date/Time Settings

- Time Zone
  - (UTC-12:00) International Date Line West to (UTC-05:00) Eastern Time (US & Canada) to (UTC+14:00) Kiribati Island
- Daylight Saving Time Settings
  - Off, On
  - Start: Month, Week, Day
  - End: Month, Week, Day
- Date Format
  - YYYY MM/DD, MM/DD/YYYY, DD/MM/YYYY
- Time Format
  - 12 Hour (AM/PM), 24 Hour
- Auto Reset Time
  - Set This Function
  - Off, On
  - Set Time: 1 to 2 to 9 (min.)
- Function After Auto Reset
  - Default Function, Selected Function
- Auto Sleep Time
  - 1 to 60 (min.)
- Auto Sleep Daily Timer
  - Set This Function
  - Off, On
  - (0:00 to 12:59 AM/PM)
- Sleep Mode Exit Time Settings
  - Set This Function
  - Off, On
  - (0:00 to 12:59 AM/PM)

### Network

#### Select Wired/Wireless LAN

- Wired LAN, Wireless LAN

#### Wireless LAN Settings

- SSID Settings
  - Select Access Point
  - Enter Manually
  - Security Settings
    - None
    - WEP
      - Open System
        - WEP Key 1 to 4
        - Shared Key
          - WEP Key 1 to 4
      - WPA/WPA2-PSK
        - Auto, AES - CCMP
  - WPS Push Button Mode
  - WPS PIN Code Mode
  - Power Save Mode
    - Off, On
  - Connection Information
    - MAC Address
    - Wireless LAN Status
    - Latest Error Information
    - Channel
    - SSID Settings
    - Security Settings
    - Power Save Mode
- Direct Connection Settings
  - Use Direct Connection
    - Off, On
  - Direct Connection Termination
    - Automatically Terminate Session
      - Off, On
      - Time Until Session Terminates: 1 to 60 (min.)
  - Access Point Mode Settings
    - Use Custom SSID
      - Off, On
      - SSID
    - Use Custom Network Key
      - Off, On
      - Network Key
    - Keep Enabled If SSID/Ntwk Key Spctd
      - Off, On
    - Config. IP Address For Direct Conn.
      - 192.168.22.1

### TCP/IP Settings

#### IP4 Settings

- IP Address Settings
  - Auto Acquire
    - Auto Acquire
      - Off
      - On
        - Select Protocol
          - Off, DHCP
          - Auto IP
            - Off, On
    - Manually Acquire
      - IP Address: 0.0.0.0
      - Subnet Mask: 0.0.0.0
      - Gateway Address: 0.0.0.0
  - DHCP Option Settings
    - Acquire Host Name
      - Off, On
    - Acquire DNS Server Address
      - Off, On
    - Acquire Domain Name
      - Off, On
    - Acquire WINS Server Address
      - Off, On
    - Acquire SMTP Server Address
      - Off, On
    - Acquire POP Server Address
      - Off, On
  - PING Command
    - Off, On

#### IP6 Settings

- Use IPv6
  - Off, On
- Stateless Address Settings
  - Stateless Address Settings
    - Off, On
  - Check Settings
    - Stateless Address
      - Prefix Length
- DHCPv6 Settings
  - Use DHCPv6
    - Off, On
  - Check Settings
    - Stateful Address
      - Prefix Length
- DHCP Option Settings
  - Acquire DNS Server Address
    - Off, On
  - Acquire Domain Name
    - Off, On
- Check IPv6 Settings
  - Off, On

#### DNS Settings

- IP4 DNS Server Address Settings
  - Primary DNS Server: 0.0.0.0
  - Secondary DNS Server: 0.0.0.0
- DNS Host Name/Domain Name Settings
  - IP4
    - Host Name
    - Domain Name
  - IP6
    - Use IPv4 Host/Domain
      - Off
      - Host Name
      - Domain Name
    - Off
    - Host Name
    - Domain Name
- DNS Dynamic Update Settings
  - IP4
    - DNS Dynamic Update
      - Off, On
      - DNS Dynamic Update Interval: 0 to 24 to 48 (hr.)
  - IP6
    - DNS Dynamic Update
      - Off, On
      - DNS Dynamic Update Interval: 0 to 24 to 48 (hr.)
- mDNS Settings
  - IP4
    - Use mDNS
      - Off, On
      - mDNS Name
  - IP6
    - Use mDNS
      - Off, On
      - mDNS Name

### Port Number Settings

- LPD
  - 1 to 515 to 65535
- RAW
  - 1 to 9100 to 65535
- WSD Multicast Discovery
  - 1 to 3702 to 65535
- HTTP
  - 1 to 80 to 65535
- Multicast Discovery
  - 1 to 427 to 65535
- POP3
  - 1 to 110 to 65535
- SMTP
  - 1 to 25 to 65535
- FTP
  - 1 to 21 to 65535
- SNMP
  - 1 to 161 to 65535

### SNMP Settings

- SNMPv1 Settings
  - Off, On
- SNMPv3 Settings
  - Off, On
- Acquire Printer Mngt. Info. from Host
  - Off, On
- Format Host Rsrcs. MIB to RFC2790
  - Off, On

### Use Dedicated Port

- Off, On

### Dedicated Port Auth. Method

- Mode 1, Mode 2

### Wait Time for Conn. at Startup

- 0 to 300 (sec.)

### Ethernet Driver Settings

- Auto Detect
  - Off
  - Communication Mode
    - Half Duplex, Full Duplex
  - Ethernet Type
    - 10BASE-T, 100BASE-TX, 1000BASE-T
- MAC Address
  - Off, On

### Use IEEE 802.1X

- Off, On

### Firewall Settings

- IP4 Address Filter
  - Outbound Filter
    - Off, On
  - Inbound Filter
    - Off, On
- IP6 Address Filter
  - Outbound Filter
    - Off, On
  - Inbound Filter
    - Off, On
- MAC Address Filter
  - Outbound Filter
    - Off, On
  - Inbound Filter
    - Off, On

### Google Cloud Print Settings

- Use Google Cloud Print
  - Off, On
- Google Cloud Print Regist. Status

### Device Settings Management

- Off, On

### Monitoring Service

- Off, On

### RMT-SW

- Off, On

### Initialize Network Settings

- Off, On

### External Interface

#### USB Settings

- Use as USB Device
  - Off, On
- Use USB Storage Device
  - Off, On

### Accessibility

- Invert Screen Colors
  - Off, On
- Brightness
  - Five Levels
- Message Display Time
  - 1 to 2 to 5 (sec.)

### Adjustment/Maintenance

#### Adjust Image Quality

- Auto Adjust Gradation
  - Full Adjust
  - Quick Adjust
  - Adjust Copy Image
- Auto Correction Settings
  - Auto Adjust Image Regularly
    - Off, On
    - When Turning Main Power ON, After Printing First Job
  - Correct Print Color Mismatch
    - After Printing First Job, When Turning Main Power ON
- Correct Print Color Mismatch
- Black Text Processing for Color
  - Feeder
    - Seven Levels
  - Platen Glass
    - Seven Levels
- Adjust Print Position
  - Multi-Purpose Tray
    - Adjust Vertically (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Vertically (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
  - Drawer 1
    - Adjust Vertically (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Front Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Vertically (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))
    - Adjust Horizontally (Back Side)
      - 0.20" to 0.00" to +0.20" (-5.0 to 0.0 to +5.0 (mm))

### WINS Settings

- WINS Resolution
  - Off, On
- WINS Server Address: 0.0.0.0

### LPD Settings

- Use LPD Printing
  - Off, On
- RX Timeout
  - 1 to 5 to 60 (min.)

### RAW Settings

- Use RAW Printing
  - Off, On
- RX Timeout
  - 1 to 5 to 60 (min.)

### WSD Settings

- Use WSD Printing
  - Off, On
- Use WSD Browsing
  - Off, On
- Use WSD Scanning
  - Off, On
- Use Computer Scanning
  - Off, On
- Use Multicast Discovery
  - Off, On

- Use FTP PASV Mode
  - Off, On
- Use HTTP
  - Off, On
- Use IPsec
  - Off, On

### Special Processing

#### Special Paper Processing

- Manual Back Side Print (2-Sided Only)
  - Multi-Purpose Tray
    - Off, On
  - Drawer 1
    - Off, On
- Rough Surface Paper Mode
  - Multi-Purpose Tray
    - Off, On
  - Drawer 1
    - Off, On
- Env. Flap Closing Prevention
  - Off, On
- Paper Wrinkle Correction
  - Off, Mode 1, Mode 2
- Paper Curl Correction
  - Off, Mode 1, Mode 2
- Reduce Ppr. Sticking at Output
  - Off, Mode 1, Mode 2
- High Humidity Mode
  - Off, On
- Low Humidity Mode
  - Off, On
- Reduce Ghosting 2
  - Off, On
- Rdc Condens. (Consec 2-Sd Prt)
  - Off, On
- Correct Void
  - Off, On
- Reduce Formation of Waterdrop Pttm.
  - Off, On
- Prevent Fogging
  - Off, On
- Correct Color Mismatch
  - Off, On
- Reduce Drum Streak
  - Off, On
- Reduce Toner Flaking
  - Off, On
- Auto Detect B&W/Color Original
  - Mode 1, Mode 2
- Rdc. Faint Print After Rplc. Cart.
  - Off, On

#### Remove Streaks from Scan Area

- Off, On

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.

### Maintenance

- Clean Fixing Assembly
- Clean ITB
- Clean Feeder
- Control Condensation
  - Off, On
  - Use Fax Memory Lock/Allow Job Printing During Process, Use Fax Memory Lock + Do Not Allow Job Printing During Process/Do Not Allow Job Printing During Process

### Function Settings

### Common

#### Paper Feed Settings

- Paper Source Auto Selection
  - Copy
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
  - Printer
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
  - Receiver/Fax / Receive
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
  - Other
    - Multi-Purpose Tray
      - Off, On
    - Drawer 1
      - Off, On
- Switch Paper Feed Method
  - Multi-Purpose Tray
    - Speed Priority, Print Side Priority
  - Drawer 1
    - Speed Priority, Print Side Priority

#### Print Settings

- Auto Delete Suspended Jobs
  - Set This Function
    - Off, On
- Set Time: 0 to 5 to 240 (min.)

#### Scan Settings

- Auto Online
  - Off, On
- Auto Offline
  - Set This Function
    - Off, On
  - Set Time: 1 to 5 to 60 (min.)

#### Generate File

- Output File Image Settings
  - YCbCr TX Gamma Value
    - Gamma 1.0, Gamma 1.4, Gamma 1.8, Gamma 2.2
  - OCR (Text Searchable) Settings
    - Smart Scan
      - Off, On

#### Fax Setup Guide

Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.


### Copy

#### Change Default Settings (Copy)



- Number of Copies
  - 1 to 999
- Paper Source
  - Multi-Purpose Tray, Drawer 1
- Density
  - Nine Levels
    - Adjust Background Density
      - Auto
        - Adjust (Manual)
          - Nine Levels
            - Density by Color
              - Red: Nine Levels
              - Green: Nine Levels
              - Blue: Nine Levels

- Copy Ratio
- Custom Ratio, 100% Direct, Auto, 400% Max, 200%, 129% STMT->LTR, 78% LGL->LTR, 64% LTR->STMT, 50%, 25% Min
- 2-Sided Printing
- Off, 1-Sided->2-Sided, 2-Sided->2-Sided, 2-Sided->1-Sided, Orig./Fin. Type
- N on 1
- Off, 2 on 1, 4 on 1, Layout
- Original Type
- Text/Photo/Map (Speed), Text/Photo/Map, Text/Photo/Map (Quality), Printed Image, Text



# Menu Route Map





Settings marked with "\*" may not be displayed depending on the model you are using or other setting items.




Settings marked with "\*" may not be displayed depending on the model you are using or other setting items.




Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.




Settings marked with "\*" may not be displayed depending on the model you are using or other setting items.



# Menu Route Map



Settings marked with "\*" may not be displayed depending on the model you are using, options, or other setting items.



**Set Destination**

**Address Book PIN**

**Management Settings**

